


## RELEASE NOTES

## ID ISC.SDK.xxx for Java

## History of Revisions



Operating System	Target		SDK Name	Notes
	32-Bit	64-Bit		
Windows Vista / 7 / 8 / 10	X	X	ID ISC.SDK.Java	
Linux	X	X	ID ISC.SDK.Java	Other than Intel CPU on request
Raspberry Pi 3 and 4	X	-	ID ISC.SDK.Raspi	Raspbian OS (Stretch and Buster)
Android	X	X	ID ISC.SDK.Android	Android 6.0 (API level 23) or higher

## Note

© Copyright 2003-2021 by FEIG ELECTRONIC GmbH  
Lange Straße 4  
D-35781 Weilburg  
Germany  
eMail: [identification-support@feig.de](mailto:identification-support@feig.de)

This manual supercedes all previous editions.  
The information contained in this manual is subject to change without notice.

**Copying of this document, and giving it to others and the use or communication of the contents thereof, is forbidden without express authority. Offenders are liable to the payment of damages. All rights are reserved in the event of the grant of a patent or the registration of a utility model or design.**

The information contained in this manual has been gathered with all due care and to the best of our knowledge. FEIG ELECTRONIC GmbH assumes no liability for the accuracy and completeness of the data in this manual. In particular, FEIG ELECTRONIC GmbH cannot be held liable for consequential damages resulting from inaccurate or incomplete information. Since even with our best efforts this document may still contain mistakes, please contact us should you find any errors.

FEIG ELECTRONIC GmbH assumes no responsibility for the use of any information contained in this manual and makes no representation that they free of patent infringement. FEIG ELECTRONIC GmbH does not convey any license under its patent rights nor the rights of others.

The installation instructions given in this manual are based on advantageous boundary conditions. FEIG ELECTRONIC GmbH does not give any guarantee promise for perfect function of an **IDENTIFICATION**-system in cross surroundings.

## General Information Regarding this Document

- The following figure formats are used:
  - 0...9: for decimal figures
  - 0x00...0xFF: for hexadecimal figures,
  - b0...1 for binary figures.
- The hexadecimal value in brackets "[ ]" marks a command.

---

## Content

---

<b>General Information Regarding this Document .....</b>	<b>3</b>
<b>Content .....</b>	<b>4</b>
<b>History of Revisions .....</b>	<b>5</b>
05.06.00 (2021-05-21).....	5
05.05.02 (2020-07-15).....	6
05.05.01 (2020-05-28).....	7
05.05.00 (2020-05-11).....	8
05.04.01 (2020-02-04) – Android only .....	9
05.04.00 (2019-11-15).....	10
05.02.00 (2019-03-15).....	11
05.01.03 (2019-02-11).....	12
05.01.00 (2018-08-15).....	13
05.00.00 (2018-07-27).....	14
05.00.00 (2018-07-06) – Beta-Version for Android.....	15
04.09.02 (2018-03-20) – 4 <sup>th</sup> Beta .....	16
04.09.00 (2017-09-29) – 3 <sup>rd</sup> Beta .....	17
04.08.01 (2017-06-08) – 2 <sup>nd</sup> Beta .....	18
04.08.00 (2017-05-02) – 1 <sup>st</sup> Beta .....	18

---

## History of Revisions

---

---

### 05.06.00 (2021-05-21)

---

#### ***General***

- Support for new reader types ECCO Smart HF-BLE and ECCO Smart 2D-HF-BLE

#### ***Features***

- Updated Config Parameters for some Readers

#### ***Changes***

- 

#### ***Bug fixes***

- 

#### ***Improvements***

- 

#### ***Discontinued Support***

---

**05.05.02 (2020-07-15)**

---

**General**

- Support for Raspberry Pi 3 Stretch and Buster
- Support for Raspberry Pi 4 Buster

**Features**

- 

**Changes**

- 

**Bug fixes**

- Bugfix in library FEISC for of a race condition, when multiple threads are used for controlling multiple readers.
- Bugfix in library FEISC for using the call order **FEISC\_BuildSendProtocol**, **FEISC\_SendProtocol** and **FEISC\_SplitRecProtocol** in combination with protocol encryption.

**Improvements**

- 

**Discontinued Support**

- Raspberry Pi 2
- Raspberry Pi Jessie operating system

---

**05.05.01 (2020-05-28)**

---

***General******Features******Changes******Bug fixes***

- bugfix for occational crashes in IBrmTable.getItemByIndex, caused by an uninitialized boolean variable

***Improvements******Discontinued Support***

---

**05.05.00 (2020-05-11)**

---

**General**

- Support for new Scanner: **ID HyWEAR compact xT**
- Support for new Reader: **ID SPAD.U**
- Support for new Reader: **ID CPR71**

**Features**

- Updated Config Parameters for some Readers

**Changes****Bug fixes**

- bugfix for DAT concerning cascade level

**Improvements**

- Improved support for ID CPR60

**Discontinued Support**



---

**05.04.01 (2020-02-04) – Android only**

---

***General***

- 

***Features***

- 

***Changes***

- 

***Bug fixes***

- Fix FEUSB version mismatch

***Improvements***

-

---

**05.04.00 (2019-11-15)**

---

**General**

- Support for new Scanner: **ID ECCO+**

**Features**

- Updated Config Parameters for some Readers

**Changes**

- 

**Bug fixes**

- 

**Improvements**

- After call of Reboot(), the Inventory Table is cleared.
- Extend **TH\_ISO15693\_STM\_ST25DVxxK** class with [0xBF] Transparent Commands for Readers not supporting [0xB1] Custom Commands for ST25DVxxK.
- Prepared for new Windows 10 certified USB Kernel Driver v3.26

**Discontinued Support**

- End of support for the following Readers:  
ID ISC.MR200  
ID ISC.LR200  
ID ISC.LR2000  
ID ISC.MRU200  
ID ISC.LRU1000  
ID ISC.LRU2000
- End of support for the following Transponder chips:  
IDS SL900A  
IDS SL13A  
KSW  
Maxim MAX66000 series

---

**05.02.00 (2019-03-15)**

---

**General**

- Support for new Scanner: **ID HyWEAR compact**
- Support for new Readers: **ID LRU500i-PoE**, **ID LRU500i-BD** and **ID MAX.U500i**
- **SDK.Raspi**: support for **Stretch OS**.

**Features**

- TagHandler class **TH\_ISO15693**: New communication methods for ISO 15693-3
  1. readMultipleBlocksEx
  2. writeMultipleBlocksEx
  3. lockMultipleBlocksEx
  4. getSystemInformationEx
  5. getMultipleBlocksSecurityStatusEx
- New static methods in **Const.ReaderType**: **isISO15693Reader**, **isISO14443Reader**, **isISO180003m3Reader**, **isEpcC1G2Reader**. These methods are also added as non-static to **IInfoGroup.ReaderInfo**.

**Changes**

- TagHandler class **TH\_ISO15693**: **getSystemInformation** has new signature.
- TagHandler class **TH\_ISO15693\_STM\_M24LR64R**: the following communication methods are removed and replaced in **TH\_ISO15693**:
  1. ReadMultipleBlocks
  2. WriteMultipleBlocks
  3. LockMultipleBlocks
  4. GetMultipleBlocksSecurityStatus

**Bug fixes**

- **IBrmTableGroup.BrmTableItem.RssiSector.GetRSSI()**: return now from all antennas

**Improvements**

-

---

**05.01.03 (2019-02-11)**

---

***General***

- Release only for Windows

***Features***

- First support for ID HyWEAR compact

***Bug fixes***

- 

***Improvements***

-

---

**05.01.00 (2018-08-15)**

---

***General***

- Release only for Android

***Features***

- 

***Bug fixes***

- 

***Improvements***

-

---

**05.00.00 (2018-07-27)**

---

**General**

- Release of new API

**Features**

- TagHandler class **TH\_ISO15693**: New communication method TransparentCommand for [0xBF] Transparent Command.
- Class **BrmTableItem**: Support for Tag Statistics for UHF Readers.
- Support for Extended Devices/Function Units.

**Changes**

- TagHandler class **TH\_ISO15693** and **TH\_EPC\_Class1\_Gen2**: Communication methods Authenticate and Challenge modified according the modifications in the Reader firmware.

**Bug fixes**

- 

**Improvements**

-

---

**05.00.00 (2018-07-06) – Beta-Version for Android**

---

**General**

- Release of new API
- The USB communication stack for Android is redesigned with Java code and currently not finalized and less tested

**Features**

- TagHandler class **TH\_ISO15693**: New communication method TransparentCommand for [0xBF] Transparent Command.
- Class **BrmTableItem**: Support for Tag Statistics for UHF Readers.
- Support for Extended devices (not applicable with Android).

**Changes**

- TagHandler class **TH\_ISO15693** and **TH\_EPC\_Class1\_Gen2**: Communication methods Authenticate and Challenge modified according the modifications in the Reader firmware.

**Bug fixes**

- No fixes

**Improvements**

- No rooted Android targets necessary for USB communication

---

**04.09.02 (2018-03-20) – 4<sup>th</sup> Beta**

---

**Features**

- No new features

**Changes**

- Repeat of DAT commands after a delay, when the call failed with timeout.

**Bug fixes**

- Linux: Bugfix for USB communication with PR101/MR101/PRH101
- TH\_EPC\_Class1\_Gen2.getEpcOfIDD: Control of length information from PC

**Improvements**

- Correction of inline documentation for IFwUpdListener.onNewFwUpdMessage



---

**04.09.00 (2017-09-29) – 3<sup>rd</sup> Beta**

---

**Features**

- Class **ReaderModule**
  - Add of communication methods Reboot, RfReset, RfOff, RfOn, SetOutput, GetInput, SetSystemClock, GetSystemClock, ReaderLogin.
  - Add of new internal interface IKeyMngGroup.
- Class **IBrmTableGroup**
  - Add of communication methods ReadBuffer, ClearBuffer, InitializeBuffer and GetBufferInfo.
- New class **IKeyMngGroup** with communication methods for setting authentication passwords.
- New **TagHandler** classes for:
  - STM ST25DV04K and STM ST25DV16/64K
  - NXP ICODE DNA
  - NXP ICODE SLIX2
- TagHandler class **TH\_EPC\_Class1\_Gen2**
  - New communication methods Select, Untraceable, Authenticate, Challenge and ReadBuffer accoding EPC class1 gen2 standard v2.0.1 and ISO/IEC 29167-x.
- TagHandler class **TH\_ISO15693**
  - New communication methods Authenticate, Challenge and ReadBuffer accoding ISO/IEC 15693-3 Amd4 and ISO/IEC 29167-x.
- New **Utility class** OutputSettings.

**Changes**

- Updated Reader Configuration namespaces in ReaderConfig.
- For ID ISC.LRU1002: Phase Angel feature for Host-Mode, Buffered-Read-Mode and Notification-Mode.
- Class **ReaderModule**
  - Remove of internal interface IExtDeviceGroup. This interface will come back later.
- Class **BrmTableItem**
  - Table elements moved into sectors. This design is close to the configured data flow from the Reader.
- Adaption in **TH\_ISO14443\_4** due to modifications in base library FETCL.
- TagHandler class **TH\_EPC\_Class1\_Gen2**
  - WriteEPC supports EPC length of 0 (zero).

**Bug fixes**

- TagHandler class **TH\_ISO14443\_4\_MIFARE\_Plus\_SL3**
  - All Read methods returns data from internal Rx buffer instead of internal Tx buffer.

---

**04.08.01 (2017-06-08) – 2<sup>nd</sup> Beta**

---

***Improvements***

- Thread-safeness improved in JNI wrapper.

---

**04.08.00 (2017-05-02) – 1<sup>st</sup> Beta**

---

***Features***

- First beta of a new API on top of the old FEDM Java library.